

AMBER Drug Discovery Boost Package

User Guide

Laboratory for Biomolecular Simulation Research
Rutgers University

February 22, 2022

1 The AMBER Drug Discovery Boost package

The AMBER Drug Discovery Boost package consists of three components, 1) **FE-MDEngine**, 2) **FE-ToolKit**, and 3) **FE-Workflow**. **FE-MDEngine** consists of the current release version of AmberTools21 and a specialized version of AMBER20 (the pmemd package) that contains the newest technologies related to alchemical free energy methods that are not yet available in the current release version of AMBER (AMBER20). The AMBER License and “patch” code mechanism enables anyone with a current AMBER license to gain advanced access to the AMBER DD Boost package for beta testing and validation prior to the official integration of these new methods into AMBER (which occurs on a 2-year cycle). **FE-ToolKit** consists of a collection of programs that implement the latest approaches for analyzing free energy simulations, and **FE-Workflow** consists of a collection of programs that are useful for the setup of alchemical free energy simulations (relative binding free energy (RBFE), relative solvation free energy (RSFE), and absolute solvation free energy (ASFE)) using **FE-MDEngine**, and analysis of such simulations using **FE-Workflow**.

Below is a list of recent references related to the different features within AMBER DD Boost package, as of February 22, 2022.

1. Tai-Sung Lee, Hsu-Chun Tsai, Abir Ganguly, Timothy J. Giese, and Darrin M. York. *Robust, Efficient and Automated Methods for Accurate Prediction of Protein-Ligand Binding Affinities in AMBER Drug Discovery Boost*, volume 1397 of *ACS Symposium Series*. November 2021. ISBN 9780841298064. doi: 10.1021/bk-2021-1397.ch007
2. Zoe Cournia, Christophe Chipot, Benoît Roux, Darrin M. York, and Woody Sherman. *Free Energy Methods in Drug Discovery—Introduction*, volume 1397 of *ACS Symposium Series*. November 2021. ISBN 9780841298064. doi: 10.1021/bk-2021-1397.ch001. URL <https://pubs.acs.org/sharingguidelines>
3. Timothy J. Giese and Darrin M. York. Variational Method for Networkwide Analysis of Relative Ligand Binding Free Energies with Loop Closure and Experimental Constraints. *J. Chem. Theory Comput.*, 17(3):1326–1336, 2021
4. Tai-Sung Lee, Bryce K. Allen, Timothy J. Giese, Zhenyu Guo, Pengfei Li, Charles Lin, T. Dwight McGee Jr., David A. Pearlman, Brian K. Radak, Yujun Tao, Hsu-Chun Tsai, Huafeng Xu, Woody Sherman, and Darrin M. York. Alchemical Binding Free Energy Calculations in AMBER20: Advances and Best Practices for Drug Discovery. *J. Chem. Inf. Model.*, 60:5595–5623, 2020
5. Tai-Sung Lee, Zhixiong Lin, Bryce K. Allen, Charles Lin, Brian K. Radak, Yujun Tao, Hsu-Chun Tsai, Woody Sherman, and Darrin M. York. Improved Alchemical Free Energy Calculations with Optimized Smoothstep Softcore Potentials. *J. Chem. Theory Comput.*, 16:5512–5525, September 2020. ISSN 1549-9626. doi: 10.1021/acs.jctc.0c00237
6. Hsu-Chun Tsai, Yujun Tao, Tai-Sung Lee, Kenneth M. Merz, and Darrin M. York. Validation of Free Energy Methods in AMBER. *J. Chem. Inf. Model.*, 60:5296–5300, November 2020. ISSN 1549-960X. doi: 10.1021/acs.jcim.0c00285

2 Availability of the AMBER Drug Discovery Boost package

The AMBER DD Boost package can be accessed from GitLab repositories set up through the Laboratory for Biomolecular Simulation Research (LBSR) at Rutgers (details are provided below). As mentioned earlier, **FE-MDEngine** consists of AmberTools21 and a specialized version of AMBER20. AmberTools21 is free of charge, and can also be downloaded directly from AmberMD.org. The AMBER20 part of **FE-MDEngine** is available only to AMBER20 license holders. **FE-ToolKit** and **FE-Workflow** are available to LBSR GitLab members (beta testers) and is currently available at no cost for non-commercial use. Active Amber

developers can also access **FE-MDEngine** through the Amber development GitLab repository, which mirrors **FE-MDEngine** in the LBSR GitLab repository.

In order to access the LBSR GitLab repositories housing the AMBER DD Boost package, a verified AMBER20 license holder will need an active GitLab account. A new GitLab account can easily be obtained at www.GitLab.com. The user first needs to send the e-mail address/username associated with the GitLab account to: Abir Ganguly at abir.ganguly@rutgers.edu or Darrin York at Darrin.York@rutgers.edu in order to be added to the GitLab repositories.

Note: if you have created a new GitLab account through a social media account such as Google or Facebook, you will need to manually set up your GitLab password in order for git clone to work.

Once added, the user will receive three separate notification emails confirming that the user has been added to the following three projects:

Laboratory for Biomolecular Simulation Research / **FE-MDEngine**

Laboratory for Biomolecular Simulation Research / **FE-ToolKit**

Laboratory for Biomolecular Simulation Research / **FE-Workflow**

Upon this confirmation the user will be able to check out the packages as follows:

With ssh-key setup in GitLab (recommended):

```
git clone git@gitlab.com:RutgersLBSR/FE-MDEngine.git
```

```
git clone git@gitlab.com:RutgersLBSR/FE-Workflow.git
```

```
git clone git@gitlab.com:RutgersLBSR/FE-ToolKit.git
```

Without ssh-key setup in GitLab:

```
git clone https://gitlab.com/RutgersLBSR/FE-MDEngine.git
```

```
git clone https://gitlab.com/RutgersLBSR/FE-Workflow.git
```

```
git clone https://gitlab.com/RutgersLBSR/FE-ToolKit.git
```

Note: We recommend that you create one directory, e.g. GitLab, and clone all three repositories inside that directory.

3 Installation of FE-MDEngine

The installation process of **FE-MDEngine** is identical to that of AMBER20, and can be installed by running the script *install_FE-MDEngine.sh* located in the **FE-MDEngine** directory. Further instructions can be found here <https://ambermd.org/Installation.php>

Note: In order to use **FE-Workflow** for AFE simulation setup, the installation of only the serial (without CUDA) version of **FE-MDEngine** is required, while to perform the AFE calculations setup by **FE-Workflow**, the installation of all versions of **FE-MDEngine**, i.e. serial and parallel (without CUDA) and serial and parallel (with CUDA) are required.

4 Installation of FE-ToolKit

FE-ToolKit can be installed by running the *INSTALL.sh* script located inside FE-ToolKit directory.

5 Purpose of the FE-Workflow

FE-Workflow consists of a collection of scripts that are designed to facilitate the setup, execution, and analysis of alchemical free energy (AFE) simulations using AMBER DD Boost. Currently, FE-Workflow can be used to perform relative binding free energy (RBFE), relative solvation free energy (RSFE), and absolute solvation free energy (ASFE) calculations. The scripts use a simplified input file, which is described in detail later in the user-guide, that provides top-level control on various important aspects of the intended AFE simulations.

Briefly, for a given system, such as a specific protein target, or a collection of small molecules, a) a list of desired transformations can be provided, b) key simulation settings can be specified, and c) initial configuration files (MD equilibrated parameter (parm) and coordinate (rst) files associated with the system and specified transformations) must be provided. FE-Workflow can then be used to generate a hierarchy of directories containing relevant parameter, coordinate, and AMBER input files and job submission scripts. FE-Workflow can also be used to analyze the free energy simulations using FE-ToolKit.

6 Contents of the FE-Workflow repository

The FE-Workflow repository contains the following folders:

- *UserGuide* - containing an user guide (this document) for setting up AFE with FE-MDEngine using FE-Workflow
- *Examples* - containing test cases for RBFE and RSFE calculations
- *bin* - containing scripts related to FE-Workflow

We are also in the process of putting documentation up on the Wiki site that will be updated on a regular basis - https://gitlab.com/RutgersLBSR/alchemical_fe/-/wikis/Setup-AFE-AMBER-DD-BOOST

7 Initial requirements of using the FE-Workflow

Following conditions must be met before using the FE-Workflow -

- AMBER should be installed and *AMBERHOME* should be defined. The AmberTools *cpptraj* and *parmed* are used by FE-Workflow during the setup process.
 - We recommend installing FE-MDEngine that comes with AmberTools21, however a standalone installation of AmberTools21 should also work.
 - For instructions related to download and installation of AmberTools, see <https://ambermd.org/AmberTools.php>
- *bin* subdirectories within FE-Workflow and FE-ToolKit should be available in \$PATH
- FE-ToolKit must be installed when using FE-Workflow in "analysis" mode.
- *python3* needs to be installed and available in \$PATH
- The software *RDKit* must be installed and python3 bindings to *RDKit* should be available in \$PYTHONPATH. *RDKit* is a popular open-source cheminformatics software, and is used by the atom-mapping algorithms within FE-Workflow.

- *RDKit* can be installed with a package manager
 - * Fedora - `sudo dnf install rdkit.x86_64 python3-rdkit.x86_64`
 - * Ubuntu - `sudo apt install python-rdkit`
- or, *RDKit* can be installed using *conda*
 - * See <http://www.rdkit.org/docs/Install.html#installationfordetails>
- folder containing initial structure and parameter files
 - For relative binding free energy (RBFE) calculations, this folder should contain, for each intended transformation (edge), PDB file(s) of the protein-ligand(s) complex(es) and parameter (mol2, lib, frmod) files for the associated ligands and any nonstandard residues present in the protein-ligand PDB file(s).
For relative and absolute solvation free energy (RSFE, ASFE) calculations, this folder should contain, for each intended transformation, parameter (mol2, lib, frmod) files for the associated ligand(s).
For further details related to input format please refer to Table 1

8 Usage of the FE-Workflow

The *setup_fe* script represents the main executable of the FE-Workflow, and can be created by running the script *makesetup_fe.sh* located in the FE-Workflow repository.

```
./makesetup_fe.sh
```

makesetup_fe.sh creates in **FE-Workflow** directory a bashrc file named **FE-Workflow.bashrc** that should be sourced before executing *setup_fe*. In the default setup, *setup_fe* is meant to be kept in the **FE-Workflow/bin** directory and, since **FE-Workflow/bin** is added to the `$PATH` variable, *setup_fe* should be available as a command line program. In most cases, this should be the most convenient way of using *setup_fe*. However, if needed, the location of *setup_fe* can be changed by changing the "\$path" variable in *setup_fe* accordingly.

9 Input file for *setup_fe*

setup_fe expects a inputfile named *input* in the directory where *setup_fe* is executed (or, the directory pointed by the "\$path" variable in *setup_fe*) that contains key settings of the alchemical free energy simulations that are going to be set up. A template input file can be generated by running the script with a flag *-h* or *-help*.

```
setup_fe -h
```

A typical input file looks like the following -

```
path_to_input=initial
system=CDK2
setupmode=0
ticalc=rbfe
stage=analysis
translist=(1h1q~1h1s 1h1q~1oi9 1oi9~1h1s)
mapmethod=2
mapinspect=0
```

```

mapnetwork=true
boxbuild=1
boxbufcom=16
boxbufaq=20
ionconc=0.15
pff=ff14SB
lff=gaff2
wm=tip4pew
mdboxshape=cubic
nlambda=11
lamschedule=yes
lams=(0 0.176834 0.229764 0.269379 0.302697 0.33229 0.359436 0.384886 0.40913 0.432518
0.455318 0.477748 0.5 0.522252 0.544682 0.567482 0.59087 0.615114 0.640564 0.66771
0.697303 0.730621 0.770236 0.823166 1)
protocol=unified
ntrials=3
cutoff=10
repex=true
nstlimti=5000
numexchgti=1000
hmr=false
notrajectory=true
scalpha=0.5
scbeta=1.0
gti_add_sc=5
gti_scale_beta=1
gti_cut=1
gti_cut_sc_on=8
gti_cut_sc_off=10
gti_lam_sch=1
gti_ele_sc=1
gti_vdw_sc=1
gti_cut_sc=2
gti_ele_exp=2
gti_vdw_exp=2
twostate=false
bidirection_aq=true
bidirection_com=true
partition=general-long-gpu
nnodes=1
ngpus=8
wallclock=3-00:00:00
path_to_data=data
exptdatafile=skip
bar=true
ccc=false
ccc_ddG=true
start=0.0

```

```
stop=100.0
check_convergence=true
showallcycles=true
```

Table 1 provides a detailed description of keywords that are specific to this input file for *setup_fe*. For keywords/flags that are specific to AMBER20 and AMBER-DD Boost refer to the AMBER20 reference manual and Table 2.

10 File infrastructure created by *setup_fe*

In **setup mode** (keyword *stage* set to 'setup' in input), *setup_fe* creates a folder named "system", as defined in the *input* file. The "system" folder will have two subdirectories, **setup** and **run**. The former (**setup**) will house the various intermediate files that were generated and used in creating the final input files, while the latter ("**run**") will contain independent subdirectories corresponding to each entry (transformation) in the keyword "*translist*" in the *input* file. These subdirectories that will have the same naming convention as provided in the *input* file, will further contain subdirectories named **com** and **aq** for RBFE calculations, or only the subdirectory **aq** for RSFE and ASFE calculations. The **com** and **aq** subdirectories correspond to complex and aqueous simulations, respectively, and will contain the final merged TI parameter and coordinate input files, template submission slurm scripts, a folder named **inputs** containing relevant AMBER input files, and production sub-folders corresponding to each specified independent trial that will house the production simulation data.

In the workflow, the starting structures are subjected to an exhaustive equilibration protocol that consists of two broad phases. In phase I, only the endstate(s) are considered (i.e. only the $\lambda=0$ state for *1-state setup* and only the $\lambda=0$ and $\lambda=1$ states for *2-state setup*). The endstates are equilibrated thoroughly using a series of minimization, constant NVT, and constant NPT simulations with varying restraints on the solute to ensure proper equilibration. Protein-ligand simulations are subjected to a longer phase I equilibration with additional steps compared to simulations of only ligand in water or vacuum (for ASFE simulations). In phase II, from the equilibrated end-point structures, all other intermediate λ windows are generated and further equilibrated, again using a series of short minimization and constant NPT simulations to generate the starting structures for the production TI simulations.

Note: The equilibration protocol, that is the order in which various equilibration steps are intended to be carried out, can be found inside the *run_alltrials.slurm* script (assigned to the *eqstage* variable), generated in the "system"/run/"com" and "system"/run/"aq" folders.

In **analysis mode** (keyword *stage* set to 'analysis' in input), *setup_fe* creates a folder named **results** in the directory in which *setup_fe* is executed. The **results** folder will contain a subdirectory **data** that will have a nested directory structure containing Energy and DV/DL data from the various simulations in the transformation network being analyzed. The **results** folder will also contain the graphmbar input file named *graphmbar.inp* for FE-ToolKit, a python script named *gmbar.py* that facilitates the generation of the graphmbar input file, the graphmbar output file named *graphmbar.out* generated by FE-ToolKit, and a simplified output file named *out* summarizing the final free energy results of the entire transformation network.

11 An example usage of *setup_fe*

Once FE-MDEngine and FE-ToolKit have been installed, and *setup_fe* has been created using the instructions above, you can test the FE-Workflow by creating a test working directory and copying an

example input file provided in **Examples** subdirectory within the **FE-Workflow** repository. Go to the test directory, rename the specific *input.** to *input*, modify the variable *path_to_input* in *input* to the location of the **initial** subdirectory within the **FE-Workflow** repository, source the **FE-Workflow.bashrc** file in **bin** subdirectory within the **FE-Workflow** repository, and execute *setup_fe*.

```
mkdir -p test-run
```

```
cd test-run
```

```
cp path-to-FE-Workflow/Examples/rbfe/input.CDK2 ./input
```

```
vi input #change path_to_input=path-to-FE-Workflow/Examples/initial
```

```
setup_fe
```


Table 1. Keywords associated with the *ProFESSA* workflow

| Keyword | Value | Description | Example |
|---------------|-----------------------|---|--|
| path_to_input | string | Path to directory that contains input files. It should contain a subdirectory <i>system</i> . | path_to_input =/home/username/afe/initial |
| system | string | Name of the system. A folder named system should be present in <i>path_to_input</i> /, and should contain the initial structure and parameter files. | system=CDK2 |
| translist | list of strings | A list of desired transformations or edges. In the case of RBFE or RSFE calculations, <i>translist</i> should be a list in which each entry consists of two molnames separated by the character "~", while in the case of ASFE calculations, <i>translist</i> should be a list of molnames. Initial structure/parameter files of these molnames should be provided in <i>path_to_input/system</i> and should be named as follows: For RBFE calculations, each molname present in <i>translist</i> should have an associated <i>molname.pdb</i> , representing the receptor-ligand complex structure and [<i>molname_0.mol2</i> <i>molname_0.lib</i> <i>molname_0.frcmod</i>], representing the ligand parameters. Parameters of additional non-standard residues, if present, can be provided as [<i>molname_1.mol2</i> <i>molname_1.lib</i> <i>molname_1.frcmod</i>], [<i>molname_2.mol2</i> <i>molname_2.lib</i> <i>molname_2.frcmod</i>], etc. For RSFE and ASFE calculations, each molname present in <i>translist</i> should have associated [<i>molname_0.mol2</i> <i>molname_0.lib</i> <i>molname_0.frcmod</i>] files. | translist=(1h1q~1h1r 1h1q~1h1s) |
| ticalc | string | Specifies nature of calculation. Acceptable values - <i>rbfe</i> , <i>rsfe</i> , <i>asfe</i> . | ticalc=rbfe |
| nlambd | integer | Number of lambda windows in TI calculation. Acceptable values - positive integers. | nlambd=21 |
| protocol | string | Protocol for running TI simulations. Acceptable value - <i>unified</i> . | protocol=unified |
| mapmethod | integer | Specifies the algorithm using which TS/TC regions are going to be determined. Acceptable values - 0, 1, 2. 0 specifies MCS algorithm. 1 specifies MCS-E algorithm. 2 specifies MCS-E2 algorithm. For a given transformation/edge <i>molname1~molname2</i> in <i>translist</i> , an atom map file, <i>molname1~molname2.map.txt</i> , is generated in the folder <i>system/setup</i> . | mapmethod=1 |
| mapinspect | integer | Allows manual inspection of TS/TC regions. Acceptable values - 0, 1, 2. 0 specifies no manual inspection. 1 specifies manual inspection. 2 specifies resume setup assuming manual inspection has been completed. If <i>mapinspect</i> is set to 2, the necessary atom map files should be present in <i>system/setup</i> folder. | mapinspect=true |
| mapnetwork | string | Specifies if network-wide consistent TS/TC regions of ligands will be generated. Acceptable values - <i>true</i> , <i>false</i> . | mapnetwork=false |

Continued on next page

Table 1 – continued from previous page

| Keyword | Value | Description | Example |
|----------------|------------------------|---|-------------------|
| boxbuild | string / integer | Specifies if and how MD boxes will be built. Acceptable values - <i>0</i> , <i>1</i> , <i>2</i> , <i>skip</i> . <i>0</i> specifies to build boxes only for "aqueous" state and not for "complex" state. <i>1</i> specifies to build boxes for both "aqueous" and "complex" states. <i>2</i> specifies to build boxes for both "aqueous" and "complex" states with identical number of water and ions. <i>skip</i> specifies to skip box building altogether. For RSFE and ASFE calculations, <i>boxbuild 0</i> and <i>1</i> are identical. | boxbuild=1 |
| boxbufcom | integer | Specifies MD box buffer for "complex" states. Relevant only for RBFE calculations. Acceptable values - positive integers. | boxbufcom=16 |
| boxbufaq | integer | Specifies MD box buffer for "aqueous" states. Relevant only for RBFE calculations. Acceptable values - positive integers. | boxbufaq=21 |
| ionconc | float | Specifies the MD box ion concentration in units of mol/L (M). Acceptable values - positive real number. | ionconc=0.15 |
| pff | string | Specifies protein forcefield. Acceptable values - <i>ff14SB</i> | pff=ff14SB |
| lff | string | Specifies ligand forcefield. Acceptable values - <i>gaff</i> , <i>gaff2</i> | lff=gaff2 |
| wm | string | Specifies water model. Acceptable values - <i>tip4pew</i> , <i>tip3p</i> | wm=tip4pew |
| mdboxshape | string | Specifies shape of MD box. Acceptable values - <i>cubic</i> | mdboxshape=cubic |
| ntrials | integer | Specifies the number of independent trials of calculation. Acceptable values - positive integers. | ntrials=10 |
| cutoff | integer | Specifies non-bonded cutoff in TI simulations. Acceptable values - positive integers. | cutoff=10 |
| replex | string | Specifies if Hamiltonian Replica Exchange will be employed. | replex=true |
| nstlimti | integer | Specifies the length of production TI simulations in units of fs. Acceptable values - positive integers. | nstlimti=5000 |
| numexchgti | integer | Specifies the number of exchanges in replica exchange TI simulations. <i>numexchgti</i> is ignored if <i>replex</i> is set to false. Acceptable values - positive integers. | numexchgti=1000 |
| hmr | string | Specifies if Hydrogen Mass Repartitioning will be used. Acceptable values - <i>true</i> , <i>false</i> . | hmr=false |
| notrajectory | string | Specifies if production trajectories will be saved during TI simulations. Acceptable values - <i>true</i> , <i>false</i> . | notrajectory=true |
| scalpha | float | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>scalpha</i> in TI simulations. Acceptable values - positive real numbers. | scalpha=0.5 |
| scbeta | float | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>scbeta</i> in TI simulations. Acceptable values - positive real numbers. | scbeta=0.5 |
| gti_add_sc | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_add_sc</i> in TI simulations. Acceptable values - positive integers. | gti_add_sc=5 |
| gti_scale_beta | float | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_scale_beta</i> in TI simulations. Acceptable values - positive real number. | gti_scale_beta=1 |
| gti_cut | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_cut</i> in TI simulations. Acceptable values - positive integers. | gti_cut=1 |
| gti_cut_sc_on | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_cut_sc_on</i> in TI simulations. Acceptable values - positive integers. | gti_cut_sc_on=8 |

Continued on next page

Table 1 – continued from previous page

| Keyword | Value | Description | Example |
|-----------------|---------|---|-------------------------------|
| gti_cut_sc_off | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_cut_sc_off</i> in TI simulations. Acceptable values - positive integers. | gti_cut_sc_off=10 |
| gti_lam_sch | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_lam_sch</i> in TI simulations. Acceptable values - positive integers. | gti_lam_sch=1 |
| gti_ele_sc | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_ele_sc</i> in TI simulations. Acceptable values - positive integers. | gti_ele_sc=1 |
| gti_vdw_sc | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_vdw_sc</i> in TI simulations. Acceptable values - positive integers. | gti_vdw_sc=1 |
| gti_cut_sc | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_cut_sc</i> in TI simulations. Acceptable values - positive integers. | gti_cut_sc=1 |
| gti_ele_exp | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_ele_exp</i> in TI simulations. Acceptable values - positive integers. | gti_ele_exp=2 |
| gti_vdw_exp | integer | Specifies the value of <i>AMBER DD BOOST</i> keyword <i>gti_vdw_exp</i> in TI simulations. Acceptable values - positive integers. | gti_vdw_exp=2 |
| twostate | string | Specifies if twostate setup will be employed in TI simulations. Acceptable values - <i>true</i> , <i>false</i> . | twostate=true |
| bidirection_aq | string | Specifies if bidirectional setup will be used for "aqueous" state TI simulations. Applicable when <i>twostate</i> is set to <i>false</i> . Acceptable values - <i>true</i> , <i>false</i> . | bidirection_aq=false |
| bidirection_com | string | Specifies if bidirectional setup will be used for "complex" state TI simulations. Applicable when <i>twostate</i> is set to <i>false</i> . Acceptable values - <i>true</i> , <i>false</i> . | bidirection_aq=false |
| stage | string | Specifies the action of the script. Acceptable values - <i>setup</i> , <i>analysis</i> . <i>setup</i> specifies script to set up TI simulations. <i>analysis</i> specifies script to perform analysis. | stage=setup |
| setupmode | integer | Specifies the mode of simulation setup. Acceptable values - <i>0</i> <i>0</i> sets up regular TI simulations. | setupmode=0 |
| partition | string | Specifies the HPC partition on which TI runs will be performed. Acceptable values - <i>null</i> , <i>name of HPC partition</i> . | partition=cpu |
| nnodes | integer | Specifies the number of nodes to be requested for a single set of TI simulations. Acceptable values - positive integer. | nnodes=1 |
| ngpus | integer | Specifies the number of gpus per node to be requested for a single set of TI simulations. Acceptable values - positive integer. | ngpus=8 |
| wallclock | string | Specifies the wallclock on TI jobs. Acceptable values - formatted time in hours:minutes:days. | wallclock=3-00:00:00 |
| path_to_data | string | Specifies the path to production runs. Default path is set to <i>system/protocol/run</i> | path_to_data=CDK2/unified/run |
| exptdatafile | string | Specifies the name of a text file containing experimental ligand binding free energies. Acceptable values - <i>skip</i> , <i>filename</i> . The text file should have two columns corresponding to <i>molname</i> (column 1) and relative ligand binding free energy (column 2). | exptdatafile=Expt.dat |
| bar | string | Specifies if BAR is going to be used for analysis instead of MBAR. Acceptable values - <i>true</i> , <i>false</i> . | bar=false |

Continued on next page

Table 1 – continued from previous page

| Keyword | Value | Description | Example |
|-------------------|--------------|---|------------------------|
| ccc | string | Specifies if cycle closure corrections are to be applied during analysis. Acceptable values - <i>true</i> , <i>false</i> . | ccc=true |
| ccc_ddG | string | Specifies if cycle closures will be applied to " <i>complex</i> " - " <i>aqueous</i> " delta delta Gs instead of " <i>complex</i> " and " <i>aqueous</i> " delta Gs, independently. Acceptable values - <i>true</i> , <i>false</i> . | ccc_ddG=true |
| start | float | Specifies the percentage of data to ignore from the beginning of TI production runs. Acceptable values - float numbers ranging from 0 to 100, and less than <i>stop</i> . | start=20.0 |
| stop | float | Specifies the percentage of data to read from the start of TI production runs. Acceptable values - float numbers ranging from 0 to 100, and greater than <i>start</i> . | stop=100.00 |
| check_convergence | string | Specifies if check of data convergence will be carried out during analysis. Acceptable values - <i>true</i> , <i>false</i> . If <i>check_convergence</i> is set to <i>true</i> , the analysis is carried out multiple times, for a range of <i>start</i> and <i>stop</i> values. | check_convergence=true |
| showallcycles | string | Specifies if the output should show information on all possible cycles within the given transformation network. Acceptable values - <i>true</i> , <i>false</i> . | showallcycles=true |

References

1. Zoe Cournia, Christophe Chipot, Benoît Roux, Darrin M. York, and Woody Sherman. *Free Energy Methods in Drug Discovery—Introduction*, volume 1397 of *ACS Symposium Series*. November 2021. ISBN 9780841298064. doi: 10.1021/bk-2021-1397.ch001. URL <https://pubs.acs.org/sharingguidelines>.
2. Timothy J. Giese and Darrin M. York. Variational Method for Networkwide Analysis of Relative Ligand Binding Free Energies with Loop Closure and Experimental Constraints. *J. Chem. Theory Comput.*, 17(3):1326–1336, 2021.
3. Tai-Sung Lee, Bryce K. Allen, Timothy J. Giese, Zhenyu Guo, Pengfei Li, Charles Lin, T. Dwight McGee Jr., David A. Pearlman, Brian K. Radak, Yujun Tao, Hsu-Chun Tsai, Huafeng Xu, Woody Sherman, and Darrin M. York. Alchemical Binding Free Energy Calculations in AMBER20: Advances and Best Practices for Drug Discovery. *J. Chem. Inf. Model.*, 60:5595–5623, 2020.
4. Tai-Sung Lee, Zhixiong Lin, Bryce K. Allen, Charles Lin, Brian K. Radak, Yujun Tao, Hsu-Chun Tsai, Woody Sherman, and Darrin M. York. Improved Alchemical Free Energy Calculations with Optimized Smoothstep Softcore Potentials. *J. Chem. Theory Comput.*, 16:5512–5525, September 2020. ISSN 1549-9626. doi: 10.1021/acs.jctc.0c00237.
5. Tai-Sung Lee, Hsu-Chun Tsai, Abir Ganguly, Timothy J. Giese, and Darrin M. York. *Robust, Efficient and Automated Methods for Accurate Prediction of Protein-Ligand Binding Affinities in AMBER Drug Discovery Boost*, volume 1397 of *ACS Symposium Series*. November 2021. ISBN 9780841298064. doi: 10.1021/bk-2021-1397.ch007.
6. Hsu-Chun Tsai, Yujun Tao, Tai-Sung Lee, Kenneth M. Merz, and Darrin M. York. Validation of Free Energy Methods in AMBER. *J. Chem. Inf. Model.*, 60:5296–5300, November 2020. ISSN 1549-960X. doi: 10.1021/acs.jcim.0c00285.

Table 2. The following table lists the keywords that are specific to **FE-MDEngine**. Brief descriptions are provided. For additional details refer to AMBER20 Reference Manual.

| Flags | Entry | Description |
|----------------|--------------------|--|
| scalpha | <i>real number</i> | The α parameter in equations 23.5 and 23.6 in AMBER20 Manual. Default value is 0 |
| scbeta | <i>real number</i> | The parameter β in equations 23.7 in AMBER20 Manual. Default value is 12 Å |
| gti_add_sc | <i>int</i> | Flag to control the non-bonded interactions between the common and softcore regions, and within the softcore regions. 1. AMBER18 default 2. AMBER20 default 5. AMBER20 with torsion term scaled |
| gti_scale_beta | <i>int</i> | Flag to control <i>scbeta</i> behavior. 0: default, original <i>scbeta</i> behavior 1. <i>scbeta</i> is defined as unit-less and scaled by σ_{ij} |
| gti_cut | <i>int</i> | 0: default in versions prior to AMBER20. 1: default, the non-bond cutoff, defined by <i>cutoff</i> , will not have effect on the internal softcore non-bonded terms. |
| gti_cut_sc_on | <i>real number</i> | Threshold distance for switching on of softcore smoothing. If undefined, <i>gti_cut_sc_on</i> is set to <i>cutoff</i> - 2 Å. Must be smaller than the value of <i>gti_cut_sc_off</i> . |
| gti_cut_sc_off | <i>real number</i> | Threshold distance for switching off of softcore smoothing. Must be smaller than the value of <i>gti_cut_sc_off</i> . |
| gti_lam_sch | <i>int</i> | Flag for λ -scheduling. 0: Default, λ -scheduling is disabled. 1: λ -scheduling is enabled. |
| gti_ele_sc | <i>int</i> | Flag for the electrostatic softcore potentials. 0: Default when <i>gti_lam_sch</i> =0, smoothstep function is not utilized. 1: SSC(2) is utilized for vdW interactions. |
| gti_cut_sc | <i>int</i> | Flag to determine if tail smoothing will be applied to softcore potentials. 0: Default, no tail smoothing to SC 1: add smoothing to SC-vdW, beginning at <i>gti_cut_sc_on</i> and ending at <i>gti_cut_sc_off</i> , using SSC(2). 2: add smoothing to SC-vdW and SC-elec, beginning at <i>gti_cut_sc_on</i> and ending at <i>gti_cut_sc_off</i> . |
| gti_ele_exp | <i>int</i> | The exponent of $r_{elec,sc}(m)$ in the softcore function; the default value is 2. |
| gti_vdw_exp | <i>int</i> | The exponent of $r_{vdw,sc}(n)$ in the softcore function; the default value is 6. |